



M A 3

PlugIn Shop

Multi Sequence Edit

Version 3.2

User Manual

Thank you for choosing "Multi Sequence Edit"! This user manual has been designed to help you make the most of our software and efficiently work with the PlugIn.

Please read this manual carefully to ensure a smooth and successful conversion process. If you have any further questions, do not hesitate to contact our support team.


We wish you success and enjoyment in using "Multi Sequence Edit"!

Table of contents


1. Quick Guide
2. Manual

Quick Guide

1. Start Multi Sequence Edit by clicking on the PlugIn.



2. Set your Changes. These Changes will be indicated by a green Background. Then click on "Select Sequences".




3. Chose the Sequences where you like to change the Edit Settings.


The Selected Sequences will be signed by a green Background.

★ Select Sequences						
Default	Color #3	Position #6	Sequence 40	Sequence 53	Sequence 70	
Sequence 2	Color #4	Position #2	Sequence 41	Sequence 54	Sequence 71	
Hello #2	Color #5	Position #3	Sequence 42	Sequence 55	Sequence 72	
Hello #3	Color #6	Sequence 30	Sequence 43	Sequence 56	Sequence 73	
Hello #4	Sequence 18	Sequence 31	Sequence 44	Sequence 57	Sequence 74	
Hello #5	Sequence 19	Sequence 32	Sequence 45	Sequence 58	Sequence 75	
Hello #6	Color #7	Sequence 33	Sequence 46	Sequence 59	Sequence 76	
Hello #7	Color #8	Sequence 34	Sequence 47	Sequence 64	Sequence 77	
Hello #8	Color #9	Sequence 35	Sequence 48	Sequence 65	Sequence 78	
Hello #9	Color #10	Sequence 36	Sequence 49	Sequence 66	Sequence 79	
Sequence 11	Color #11	Sequence 37	Sequence 50	Sequence 67	Sequence 80	
Sequence 12	Position #4	Sequence 38	Sequence 51	Sequence 68	Sequence 81	
Color #2	Position #5	Sequence 39	Sequence 52	Sequence 69	Sequence 82	

4. Close the Seclection Window by clicking on the X in the upper Right Corner.




5. Click on "Apply Changes" to execute your changes.



Manual

1. Start Multi Sequence Edit by clicking on the Plugin.




2. Set your Changes. These Changes will be indicated by a green Background.

This is the representation of an Edit Settings with the current default settings.

To change a setting, please click on the corresponding field.x

The field will be highlighted in green to indicate that this parameter will be changed during later execution.



At **Name**, a new name can be assigned. If multiple sequences are edited simultaneously, these sequences will be additionally numbered, as the same name cannot exist twice.

Scribble and **Appearances** can be selected from their respective pools. Upon execution, they will then be assigned to the selected sequences.

In the **Note** section, text can be entered which will then be applied to all selected sequences.

In all other fields, the procedure is the same as in a single sequence.
Each function can be found in the grandMA3 User Manual
under the keyword 'Sequence Edit Settings'.


3. Then click on 'Select Sequences' to choose the sequences to be edited.
4. Select the sequences for which you would like to change the Edit Settings.
The selected sequences will be highlighted with a green background
to indicate that they have been chosen.

★ Select Sequences					
Default	Color #3	Position #6	Sequence 40	Sequence 53	Sequence 70
Sequence 2	Color #4	Position #2	Sequence 41	Sequence 54	Sequence 71
Hello #2	Color #5	Position #3	Sequence 42	Sequence 55	Sequence 72
Hello #3	Color #6	Sequence 30	Sequence 43	Sequence 56	Sequence 73
Hello #4	Sequence 18	Sequence 31	Sequence 44	Sequence 57	Sequence 74
Hello #5	Sequence 19	Sequence 32	Sequence 45	Sequence 58	Sequence 75
Hello #6	Color #7	Sequence 33	Sequence 46	Sequence 59	Sequence 76
Hello #7	Color #8	Sequence 34	Sequence 47	Sequence 64	Sequence 77
Hello #8	Color #9	Sequence 35	Sequence 48	Sequence 65	Sequence 78
Hello #9	Color #10	Sequence 36	Sequence 49	Sequence 66	Sequence 79
Sequence 11	Color #11	Sequence 37	Sequence 50	Sequence 67	Sequence 80
Sequence 12	Position #4	Sequence 38	Sequence 51	Sequence 68	Sequence 81
Color #2	Position #5	Sequence 39	Sequence 52	Sequence 69	Sequence 82


4.a The new feature introduced in software version 3.2, "Import" selected , allows you to select sequences via the command line and automatically imports these sequences when the plugin is started.

Use the Command line: **Select Sequence X thru Y**

Then click the Import Button.



4.b In addition to the sequence import feature, version 3.2 introduces the following new features



"Hide Inactive" Option:

This feature helps to declutter your workspace by hiding sequences that do not have an active "Current Cue"


"Hide Empty" Option:

This feature hides sequences that only contain the default cues "CueZero" and "OffCue".


"Keep Selection" Checkbox:

By enabling this checkbox, your previous sequence selections are preserved, making it easier to continue work from where you left off without having to reselect the sequences each time the plugin is opened.

- Once you have selected all the sequences you want to edit, close the selection window by clicking on the X in the upper right corner.



- Now that you have made all the necessary settings, click on "Apply Changes" to execute your changes.



Thank you for your attention and interest in our user manual.

We hope this manual has assisted you in making the desired settings. Should you have any further questions or require assistance, please do not hesitate to contact us at any time.

Contact

ma3.plugin.shop@freenet.de